

## GEMPAK Grid Diagnostic Functions

# APPENDIX B1

## GRID DIAGNOSTIC FUNCTIONS

The following describes the computation of GEMPAK grid diagnostic functions.

Each grid in a grid file is identified by a parameter name, time, level, and vertical coordinate. A scalar grid is a single grid, while a vector grid is composed of two grids containing the u and v components.

The parameter name is used to retrieve a grid from the file, with a few exceptions: Certain special parameters will be computed from other data in the grid file if the parameter name itself is not found in the grid file. These special scalar parameters are

TMPK	DWPK	TVRK	MIXR*	THTA*	DRCT	TMWK*
TMPC	DWPC	TVRC	SMXR	STHA	SPED	TMWC
TMPF	DWPF	TVRF	MIXS	THTE*	RELH	TMWF
		THES*	SMXS	STHE		

where \* indicates names which also may be used as operators. Mixing ratio will be computed automatically from dewpoint temperature, specific humidity or vapor pressure, if a pressure grid exists.

The stability indices will be computed automatically from temperature, dewpoint temperature, and wind speed and direction. These special scalar parameters are

CTOT	VTOT	TOTL	KINX	SWET
------	------	------	------	------

Haines Indices for fire weather detection will be computed automatically from temperature and dewpoint at three different levels. These scalar parameters are:

LHAN	Low elevation Haines Index
MHAN	Middle elevation Haines Index
HHAN	High elevation Haines Index

The Heat Index, HEAT, will also be automatically computed from the temperature and relative humidity.

In addition, precipitation will be converted from inches (I) to millimeters (M) and vice versa, if the grids are named P\_\_M or P\_\_I. The middle numeric characters give the time interval over which the precipitation accumulated. For example, P24M is a 24-hour precipitation total.

The units for sea surface temperature (SST\_), maximum temperature (TMX\_) and minimum temperature (TMN\_) will be converted automatically. The underscore may

## GEMPAK Grid Diagnostic Functions

be K, C or F.

These special scalar parameter names denote constant value grids:

<b>DTR</b>	<b>Conversion factor for degrees to radians = <math>\text{PI} / 180</math></b>
<b>E</b>	<b>Base of natural logarithms = 2.71828182</b>
<b>GRAVTY</b>	<b>Gravitational constant = 9.80616 (note spelling)</b>
<b>KAPPA</b>	<b>Gas constant/specific heat = 2/7</b>
<b>PI</b>	<b>= 3.14159265</b>
<b>RTD</b>	<b>Conversion factor for radians to degrees = <math>180 / \text{PI}</math></b>
<b>nnn</b>	<b>Any number (i.e., 2, -10.2, ... )</b>

Another class of special parameter names provides information at grid points depending on the navigation of the grid file:

<b>CORL</b>	Coriolis force = $2 \cdot \text{OMEGA} \cdot \text{SIN}(\text{LATR})$
<b>LATR</b>	Latitude in radians
<b>LONR</b>	Longitude in radians
<b>XVAL</b>	Value of the x coordinate in graph coordinates
<b>YVAL</b>	Value of the y coordinate in graph coordinates
<b>MSFX</b>	Map scale factor in the x direction
<b>MSFY</b>	Map scale factor in the y direction
<b>LAND</b>	Land array; land=1, sea=RMISSD
<b>SEA</b>	Sea array; sea=1, land=RMISSD

Finally, scalar grids may be identified by their location within the grid file. The grid number must be prefixed with the symbol #. Note that grids may be renumbered as grids are added to or deleted from the file.

Vector grids are two separate grids containing the u and v components. Special vector parameter names may be used to identify the following vectors:

<b>WND</b>	Total wind
<b>GEO*</b>	Geostrophic wind
<b>AGE*</b>	Ageostrophic wind
<b>ISAL*</b>	Isallobaric wind
<b>THRM*</b>	Thermal wind

where \* indicates names that also may be used as operators. Note that all of these wind vectors will have u and v components in meters per second. The total wind must be stored as UWND and VWND in the grid file if the components are north relative and as UREL and VREL if the components are grid relative.

Time, level, and vertical coordinate may be specified in GDATTIM, GLEVEL and GVCORD. However, any of these values may be overridden by in line parameters appended to an operand in the form of ^time@level%ivcord. In-line parameters are only allowed for operands, since they modify parameters for individual grids. The in-

## GEMPAK Grid Diagnostic Functions

line parameters may be entered individually or in combinations in any order.

If more than one file is opened, +n may also be used as an in-line parameter, where n is the number corresponding to the position of the file name entered in GDFILE. If +n is omitted, the first file is used.

Grid operators may be nested, allowing a complicated diagnostic function to be computed. One limitation is that layer and time range operators expect to work on operands read directly from the grid file or computed from special names.

In the following list of diagnostic operators, scalar operands are named  $S_i$  and vector operands are  $V_i$ . Lower case u and v refer to the grid relative components of a vector. All meteorological output grids are in MKS units, except as noted. Operators using PR\_ functions are described in the GEMPAK PARAMETER APPENDIX. All scalar and vector differential operators are valid in any map projection for which the map scale factors can be computed. At present, this applies for the stereographic, cylindrical and conic projections available in GEMPAK. In the definitions below, only the cartesian form of the operators is shown. The general curvilinear coordinate forms involving the scale factors are not given.

The operators which are designated for use in polar coordinates are specific to that coordinate system.

### SCALAR OUTPUT GRID

Algebraic and trigonometric functions (angles are expressed in radians):

<b>ABS</b>	<b>Absolute value</b> ABS (S)
<b>ACOS</b>	<b>Arc cosine function</b> ACOS (S)
<b>ASIN</b>	<b>Arc sine function</b> ASIN (S)
<b>ATAN</b>	<b>Arc tangent function</b> ATAN (S)
<b>ATN2</b>	<b>Arc tangent function</b> $ATN2 (S1, S2) = ATAN ( S1 / S2 )$
<b>COS</b>	<b>Cosine function</b> COS (S)
<b>EXP</b>	<b>Exponential to real</b> $EXP (S1, S2) = S1 ** S2$
<b>EXPI</b>	<b>Exponential to integer</b>

## GEMPAK Grid Diagnostic Functions

	$EXP(S1, S2) = S1^{**} NINT(S2)$
<b>LN</b>	<b>Natural logarithm</b> $LN(S) = LOG(S)$
<b>LOG</b>	<b>Base 10 logarithm</b> $LOG(S) = LOG10(S)$
<b>SIN</b>	<b>Sine function</b> $SIN(S)$
<b>SQRT</b>	<b>Square root</b> $SQRT(S)$
<b>TAN</b>	<b>Tangent function</b> $TAN(S)$
<b>ADD</b>	<b>Addition</b> $ADD(S1, S2) = S1 + S2$
<b>MUL</b>	<b>Multiplication</b> $MUL(S1, S2) = S1 * S2$
<b>QUO</b>	<b>Division</b> $QUO(S1, S2) = S1 / S2$
<b>SUB</b>	<b>Subtraction</b> $SUB(S1, S2) = S1 - S2$
<b>SLT</b>	<b>Less than function</b> $SLT(S1, S2) = S1 < S2$
<b>SLE</b>	<b>Less than/equal to</b> $SLE(S1, S2) = S1 <= S2$
<b>SGT</b>	<b>Greater than function</b> $SGT(S1, S2) = S1 > S2$
<b>SGE</b>	<b>Greater than/equal to</b> $SGE(S1, S2) = S1 >= S2$
<b>SBTW</b>	<b>Between function</b> $SBTW(S1, S2, S3) = S1 > S2 \text{ AND } S1 < S3$
<b>BOOL</b>	<b>Boolean function</b> $BOOL(S)$
<b>MASK</b>	<b>Masking function</b> $MASK(S1, S2) = RMISSD \text{ IF } S2 = RMISSD, = S1 \text{ otherwise}$
<b>MISS</b>	<b>Missing value replace</b> $MISS(S1, S2) = S2 \text{ if } S1 = RMISSD, = S1 \text{ otherwise}$
<b>ADV</b>	<b>Advection</b> $ADV(S, V) = - (u * DDX(S) + v * DDY(S))$
<b>AVG</b>	<b>Average</b>

## GEMPAK Grid Diagnostic Functions

- AVG ( S1, S2 ) = ( S1 + S2 ) / 2
- AVOR Absolute vorticity**  
AVOR ( V ) = VOR ( V ) + CORL
- BVSQ Brunt-Vaisala frequency squared in a layer**  
BVSQ ( THTA ) = [ GRAVITY \* LDF ( THTA ) ] / [ LAV ( THTA ) \* DZ ] in PRES coordinates  
= - ( RDGAS / GRAVITY ) \* LAV ( THTA ) \* ( LAV ( PRES ) / 1000 ) \*\* KAPPA \* LDF ( PRES ) / LAV ( PRES ) in THTA coordinates  
DZ = change in height across the layer
- CROS Vector cross product magnitude**  
CROS ( V1, V2 ) = u1 \* v2 - u2 \* v1
- DDEN Density of dry air ( kg / m\*\*3 )**  
DDEN ( PRES, TMPC ) = PR\_DDEN ( PRES, TMPC )
- DDR Partial derivative with respect to R**  
DDR ( S ) is computed using centered finite differences, with backward or forward differences at the boundary. Polar coordinates are assumed, and ( R, THETA ) maps into ( X, Y ).
- DDT Time derivative**  
DDT ( S ) = ( S ( time1 ) - S ( time2 ) ) / ( time1 - time2 ) where the time difference is in seconds.
- DDX Partial derivative with respect to X**  
DDX ( S ) is computed using centered finite differences, with backward or forward differences at the boundary.
- DDY Partial derivative with respect to Y**  
DDY ( S ) is computed using centered finite differences, with backward or forward differences at the boundary.
- DEF Total deformation**  
DEF ( V ) = ( STR ( V ) \*\* 2 + SHR ( V ) \*\* 2 ) \*\* .5
- DIRN North relative direction of a vector**  
DIRN ( V ) = PR\_DRCT ( UN ( V ), VN ( V ) )
- DIRR Grid relative direction of a vector**  
DIRR ( V ) = PR\_DRCT ( u, v )
- DIV Divergence**  
DIV ( V ) = DDX ( u ) + DDY ( v )
- DOT Vector dot product**  
DOT ( V1, V2 ) = u1 \* u2 + v1 \* v2
- DTH Partial derivative with respect to THETA**  
DTH ( S ) is computed using centered finite differences, with backward or forward differences at the boundary. Polar coordinates are assumed, and ( R, THETA ) maps into ( X, Y ).
- FOSB Fosberg index, also called Fire Weather Index.**  
FOSB ( TMPC, RELH, SPED ) is computed with an empirical formula using surface temperature, relative humidity, and wind speed at the 2 meter or 10 meter level, or the mix of the two. High values in-

## GEMPAK Grid Diagnostic Functions

dicate high flame lengths and rapid drying.

- FCNT**      **Coriolis force at the center of a polar coordinate grid**  
 FCNT ( S ) can be computed only for lat/lon grids which have been mapped to polar (R,THETA) coordinates and or which the center lat/lon have been stored with each grid.
- FRNT**      **Frontogenesis ( K / 100 km / 3 h )**  

$$FRNT ( THTA, V ) = 1/2 * CONV * MAG ( GRAD ( THTA ) ) * ( DEF * COS ( 2 * BETA ) - DIV )$$

$$CONV = \text{unit conversion factor} = 1.08E4 * 1.E5$$

$$BETA = ASIN ( ( - COS ( DELTA ) * DDX ( THTA ) - SIN ( DELTA ) * DDY ( THTA ) ) / MAG ( GRAD ( THTA ) ) )$$

$$DELTA = 1/2 ATAN ( SHR / STR )$$
- GWFS**      **Horizontal smoothing using normally distributed weights**  
 GWFS ( S,N ) with theoretical response of 1/e for N \* delta-x wave. Increasing N increases the smoothing.
- HIGH**      **Relative maxima over a grid**  
 HIGH ( S, RADIUS ) where RADIUS defines a square region of grid points. The region is a moving search area in which all points are compared to derive a relative maximum.
- JCBN**      **Jacobian determinant**  

$$JCBN ( S1, S2 ) = DDX ( S1 ) * DDY ( S2 ) - DDY ( S1 ) * DDX ( S2 )$$
- KNTS**      **Convert meters / second to knots**  

$$KNTS ( S ) = PR\_MSKN ( S ) = S * 1.9438$$
- LAP**      **Laplacian operator**  

$$LAP ( S ) = DIV ( GRAD ( S ) )$$
- LAV**      **Layer average (2 levels)**  

$$LAV ( S ) = ( S ( \text{level1} ) + S ( \text{level2} ) ) / 2.$$
- LDF**      **Layer difference (2 levels)**  

$$LDF ( S ) = S ( \text{level1} ) - S ( \text{level2} )$$
- LOWS**      **Relative minima over a grid**  
 LOWS ( S, RADIUS ) where RADIUS defines a square region of grid points. The region is a moving search area in which all points are compared to derive a relative minimum.
- MAG**      **Magnitude of a vector**  

$$MAG ( V ) = PR\_SPED ( u, v )$$
- MASS**      **Mass per unit volume in a layer**  

$$MASS = 100 * LDF ( PRES ) / ( GRAVTY * ( \text{level1} - \text{level2} ) )$$

The 100 converts mb to Pascals. Level1 and level2 are also converted to Pascals when VCOORD = PRES. The volume is expressed in units of m \* m \* (units of the vertical coordinate). This is an operand.
- MDIV**      **Layer-average mass divergence**  

$$MDIV ( V ) = DIV ( [ MASS * LAV ( u ), MASS * LAV ( v ) ] )$$
- MIXR**      **Mixing ratio**

## GEMPAK Grid Diagnostic Functions

MIXR ( DWPC, PRES ) = PR\_MIXR ( DWPC, PRES )

The units are kg/kg internally, but g/kg on output.

**MRAD Magnitude of storm relative radial wind**

MRAD ( V, LAT, LON, DIR, SPD ) = DOT ( Vrel, R )

where Vrel is the velocity minus the storm motion vector specified by DIR and SPD, and R is a unit vector tangent to a great circle arc from the storm center specified by LAT, LON to a grid point.

**MSDV Layer-average mass-scalar flux divergence**

MSDV ( S, V ) = DIV ( [ MASS \* LAV (S) \* LAV (u), MASS \* LAV (S) \* LAV (v) ] )

Note: MASS is computed using the in-line parameter values for V rather than those for S.

**MSFC Psuedo angular momentum (for cross sections)**

MSFC ( V ) = NORMV ( V ) + CORL \* DIST

DIST is the distance along the cross section in meters. The units for the M-surface are expressed in m/s.

**MTNG Magnitude of storm relative tangential wind**

MTNG ( V, LAT, LON, DIR, SPD ) = DOT ( Vrel, k X R )

where Vrel is the velocity minus the storm motion vector specified by DIR and SPD, and R is a unit vector tangent to a great circle arc from the storm center specified by LAT, LON to a grid point. k denotes the local vertical unit vector.

**NORM Scalar vector component normal to a cross section**

NORM ( V ) = DOT ( V, unit normal vector )

If the starting point for the cross section is on the left, the unit normal vector points into the cross section plane.

**PLAT Latitude at each point in polar coordinates**

PLAT ( S )

Note: only the header, which contains the center latitude and longitude, is used.

**PLON Longitude at each point in polar coordinates**

PLON ( S )

Note: only the header, which contains the center latitude and longitude, is used.

**POIS Solve Poisson eqn. of a forcing function with the given boundary values**

POIS ( S1, S2 ) where S1 is the forcing function grid and S2 is the boundary value.

The equation LAP (POIS) = S1 is solved for POIS.

**POLF Coriolis force at each point in polar coordinates**

POLF ( S )

Note: only the header, which contains the center latitude and longitude, is used.

**PVOR Potential vorticity in a layer**

PVOR ( S, V ) = - GRAVITY \* AVOR ( VLAV (V) ) \* LDF ( THTA ) / ( 100 \* LDF ( PRES ) )

The 100 converts millibars to Pascals.

Units are Kelvins / meters / Pascals / seconds\*\*3 (note that GRAVITY is included).

## GEMPAK Grid Diagnostic Functions

PVOR works on a layer

in PRES or THTA coordinates. In isobaric coordinates, the scalar operand, S, is THTA, THTE, or THES. In isentropic coordinates, the scalar operand, S, is PRES. Multiplying by 10\*\*6 gives standard PV units.

- RELH**      **Relative humidity**  
RELH ( TEMP, DWPT ) = PR\_RELH ( TEMP, DWPT )
- RICH**      **Richardson stability number in a layer**  
RICH ( V ) = GRAVITY \* DZ \* LDF (THTA) / ( LAV (THTA) \* MAG ( VLDF (V) ) \*\* 2 )  
Note: DZ = change in height across the layer.  
RICH can be evaluated in PRES, THTA or HGHT vertical coordinate.
- ROSS**      **Rosby number**  
ROSS ( V1, V2 ) = MAG ( INAD ( V1, V2 ) ) / ( CORL \* MAG ( V1 ) )
- SAVG**      **Average over whole grid**  
SAVG ( S ) = average of all non-missing grid point values
- SAVS**      **Average over subset grid**  
SAVS ( S ) = average of all non-missing grid point values in the subset area
- SDIV**      **Flux divergence of a scalar**  
SDIV ( S, V ) = S \* DIV ( V ) + DOT ( V, GRAD ( S ) )
- SHR**      **Shear deformation**  
SHR ( V ) = DDX ( v ) + DDY ( u )
- SM5S**      **Smooth scalar grid using a 5-point smoother**  
SM5S ( S ) = .5 \* S (i,j) + .125 \* ( S (i+1,j) + S (i,j+1) + S (i-1,j) + S (i,j-1) )
- SM9S**      **Smooth scalar grid using a 9-point smoother**  
SM5S ( S ) = .25 \* S (i,j) + .125 \* ( S (i+1,j) + S (i,j+1) + S (i-1,j) + S (i,j-1) ) + .0625 \* ( S (i+1,j+1) + S (i+1,j-1) + S (i-1,j+1) + S (i-1,j-1) )
- STAB**      **Thermodynamic stability within a layer (lapse rate)**  
STAB ( TMPC ) = LDF ( TMPC ) / DZ in PRES coordinates.  
= - ( RDGAS / GRAVITY ) \* LAV (THTA) \* ( LAV (PRES) / 1000 ) \*\* KAPPA \*  
LDF (PRES) / LAV (PRES) in THTA coordinates  
DZ = change in height across the layer.  
Units are degrees / kilometer.
- STR**      **Stretching deformation**  
STR ( V ) = DDX ( u ) - DDY ( v )
- TANG**      **Scalar vector component tangential to a cross section**  
TANG ( V ) = DOT ( V, unit tangent vector )  
If the starting point for the cross section is on the left, the unit tangent vector points to the right.
- TAV**      **Time average (2 times)**  
TAV ( S ) = ( S (time1) + S (time2) ) / 2.
- TDF**      **Time difference (2 times)**



## GEMPAK Grid Diagnostic Functions

	TDF (S) = S (time1) - S (time2)
<b>THES</b>	<b>Saturated equivalent potential temperature in Kelvin</b> THES (PRES, TMPC) = PR_THTE (PRES, TMPC, TMPC)
<b>THTA</b>	<b>Potential temperature in Kelvin</b> THTA ( TMPC, PRES ) = PR_THTA ( TMPC, PRES )
<b>THTE</b>	<b>Equivalent potential temperature in Kelvin</b> THTE (PRES, TMPC, DWPC) = PR_THTE (PRES, TMPC, DWPC)
<b>THWC</b>	<b>Wet bulb potential temperature in Celsius</b> THWC (PRES, TMPC, DWPC) = PR_THWC (PRES, TMPC, DWPC)
<b>TMST</b>	<b>Parcel temperature in Kelvin along a moist adiabat</b> TMST (THTE, PRES) = PR_TMST (THTE, PRES, GUESS)  where THTE is the equivalent potential temperature at the input GLEVEL, PRES is the pressure level at which the parcel temperature is valid, and GUESS is a guess-field calculated automatically.
<b>TMWK</b>	<b>Wet bulb temperature in Kelvin</b> TMWK (PRES, TMPK, RMIX) = PR_TMWK (PRES, TMPK, RMIX)
<b>UN</b>	<b>North relative u component</b> UN ( V ) = zonal wind component
<b>UR</b>	<b>Grid relative u component</b> UR ( V ) = u
<b>VN</b>	<b>North relative v component</b> VN ( V ) = meridional wind component
<b>VOR</b>	<b>Vorticity</b> VOR ( V ) = DDX ( v ) - DDY ( u )
<b>VR</b>	<b>Grid relative v component</b> VR ( V ) = v
<b>WNDX</b>	<b>WINDEX (index for microburst potential)</b> WNDX (S1, S2, S3, S4) = 2.5 * SQRT (HGHTF * RATIO * (GAMMA**2 - 30 + MIXRS - 2 * MIXRF ) )  TMPCS = surface temperature = S1 HGHTF = AGL Height of Freezing level = S2 MIXRS = surface mixing ratio = S3 MIXRF = freezing level mixing ratio = S4 RATIO = MIXRS / 12 if MIXRS < 12, = 1 otherwise GAMMA = TMPCS / HGHTF
<b>WSHR</b>	<b>Magnitude of the vertical wind shear in a layer</b>

## GEMPAK Grid Diagnostic Functions

WSHR ( V ) = MAG [ VLDF ( V ) ] / DZ in PRES coordinates.

= - ( RDGAS / GRAVITY ) \* LAV (THTA) \* ( LAV (PRES) / 1000 ) \*\* KAPPA \*

LDF (PRES) / LAV (PRES) in THTA coordinates.

DZ = change in height across the layer

WSHR can be evaluated in PRES, THTA, or HGHT coordinate.

### XAV

#### Average along a grid row

XAV ( S ) = ( S ( X1 ) + S ( X2 ) + ... + S ( KXD ) ) / KNT

KXD = number of points in row

KNT = number of non-missing points in row

XAV for a row is stored at every point in that row.

In polar coord., XAV is the average along a radial.

### XSUM

#### Sum along a grid row

XSUM ( S ) = ( S ( X1 ) + S ( X2 ) + ... + S ( KXD ) )

KXD = number of points in row

XSUM for a row is stored at every point in that row. In polar coord., XSUM is the sum along a radial.

### YAV

#### Average value along a grid column

YAV ( S ) = ( S ( Y1 ) + S ( Y2 ) + ... + S ( KYD ) ) / KNT

KYD = number of points in column

KNT = number of non-missing points in column

YAV for a column is stored at every point in that column. For polar coordinates, YAV is the average around a circle. If the theta coordinate starts at 0 degrees and ends at 360 degrees, the first radial is not used in computing the average.

### YSUM

#### Sum along a grid column

YSUM ( S ) = ( S ( Y1 ) + S ( Y2 ) + ... + S ( KYD ) )

KYD = number of points in column

YSUM for a column is stored at every point in that column. For polar coordinates, YSUM is the sum around a circle. If the theta coordinate starts at 0 degrees and ends at 360 degrees, the first radial is not used in computing the sum.

## VECTOR OUTPUT GRID

### AGE Ageostrophic wind

AGE ( S ) = [ u ( OBS ) - u ( GEO(S) ), v ( OBS ) - v ( GEO(S) ) ]

### CIRC Circulation (for cross sections)

CIRC ( V, S ) = [ TANG ( V ), S ]

### DVDX Partial x derivative of a vector

DVDX ( V ) = [ DDX ( u ), DDX ( v ) ]

## GEMPAK Grid Diagnostic Functions

**DVDY      Partial y derivative of a vector**

$$DVDY ( V ) = [ DDY ( u ), DDY ( v ) ]$$

**GEO        Geostrophic wind**

$$GEO ( S ) = [ - DDY ( S ) * const / CORL, DDX ( S ) * const / CORL ]$$

const	S	vert coord
GRAVTY ZMSL	none	
GRAVTY HGHT	PRES	
1	PSYM	THTA
100/RO PRES	HGHT	

$$RO = PR\_DDEN ( PRES, TMPC )$$

**GRAD      Gradient of a scalar**

$$GRAD ( S ) = [ DDX ( S ), DDY ( S ) ]$$

**GWFV      Horizontal smoothing using normally distributed weights**

GWFV (V,N) with theoretical response of 1/e for N \* delta-x wave. Increasing N increases the smoothing.

**INAD      Inertial advective wind**

$$INAD ( V1, V2 ) = [ DOT ( V1, GRAD ( u2 ) ), DOT ( V1, GRAD ( v2 ) ) ]$$

**ISAL      Isallobaric wind**

$$ISAL ( S ) = [ - DDT ( v ( GEO(S) ) ) / CORL, DDT ( u ( GEO(S) ) ) / CORL ]$$

**KCRS      Unit vector k cross a vector**

$$KCRS ( V ) = [ -v, u ]$$

**KNTV      Convert meters / second to knots**

$$KNTV ( V ) = [ PR\_MSKN ( u ), PR\_MSKN ( v ) ]$$

**LTRN      Layer-averaged transport of a scalar**

$$LTRN ( S, V ) = [ MASS * LAV ( S ) * LAV ( u ), MASS * LAV ( S ) * LAV ( v ) ]$$

Note: MASS is computed using the in-line parameter values for V rather than those for S.

**NORMV    Vector component normal to a cross section.**

$$NORMV ( V ) = NORM ( V ) * unit normal vector$$

## GEMPAK Grid Diagnostic Functions

### **QVEC Q-vector at a level ( K / m / s )**

$QVEC ( S, V ) = [ - ( DOT ( DVDX ( V ), GRAD ( S ) ) ),$   
 $- ( DOT ( DVDY ( V ), GRAD ( S ) ) ) ]$  where S can be any thermal  
parameter, usually THTA.

### **QVCL Q-vector of a layer ( mb / m / s )**

$QVCL ( THTA, V ) = ( 1 / ( D ( THTA ) / DP ) ) *$   
 $[ ( DOT ( DVDX ( V ), GRAD ( THTA ) ) ),$   
 $( DOT ( DVDY ( V ), GRAD ( THTA ) ) ) ]$

### **RAD Storm relative radial wind**

$RAD ( V, LAT, LON, DIR, SPD ) = SMUL ( DOT ( Vrel, R ), R )$   
where Vrel is the velocity minus the storm motion  
specified by DIR and SPD, and R is a unit vector  
tangent to a great circle arc from the storm center  
specified by LAT, LON to a grid point.

### **ROT Coordinate rotation**

$ROT ( angle, V ) = [ u * COS ( angle ) + v * SIN ( angle ),$   
 $-u * SIN ( angle ) + v * COS ( angle ) ]$

### **SMUL Multiply a scalar with each component of a vector**

$SMUL ( S, V ) = [ S * u, S * v ]$

### **SM5V Smooth vector grid using a 5-point smoother**

$SM5V ( V ) = .5 * V ( i,j ) + .125 * ( V ( i+1,j ) + V ( i,j+1 ) +$   
 $V ( i-1,j ) + V ( i,j-1 ) )$

### **SQUO Vector division by a scalar.**

$SQUO ( S, V ) = [ u / s, v / s ]$

### **TANGV Vector component tangential to a cross section.**

$TANGV ( V ) = TANG ( V ) * \text{unit tangent vector}$

### **THRM Thermal wind**

$THRM ( S ) = [ u ( GEO(S) ) ( level1 ) - u ( GEO(S) ) ( level2 ),$   
 $v ( GEO(S) ) ( level1 ) - v ( GEO(S) ) ( level2 ) ]$

### **TNG Storm relative tangential wind**

$TNG ( V, LAT, LON, DIR, SPD ) = SMUL ( DOT ( Vrel, k X R ), k X R )$   
where Vrel is the velocity minus the storm motion vector speci-  
fied by DIR and SPD, and R is a unit vector tangent to a great circle arc from the storm  
center specified by LAT, LON to a grid point. k denotes the local vertical unit vector.

### **VADD Add the components of two vectors**

$VADD ( V1, V2 ) = [ u1+u2, v1+v2 ]$

### **VASV Vector component of V1 along V2**

$VASV ( V1, V2 ) = [ DOT ( V1,V2 ) / MAG ( V2 ) ** 2 ] * V2$

### **VAVG Average over whole grid**

## GEMPAK Grid Diagnostic Functions

VAVG ( V ) = average of all non-missing grid point values

**VAVS      Average over subset grid**

VAVS ( V ) = average of all non-missing grid point values in  
the subset area

**VECN      Create a vector grid from two north relative scalar components**

VECN ( S1, S2 ) = [ S1, S2 ]

**VECR      Create a vector grid from two grid relative scalar components**

VECR ( S1, S2 ) = [ S1, S2 ]

**VLAV      Layer average for a vector**

VLAV ( V ) = [ ( u (level1) + u (level2) ) / 2.,  
( v (level1) + v (level2) ) / 2. ]

**VLDF      Layer difference for a vector**

VLDF ( V ) = [ u (level1) - u (level2),  
v (level1) - v (level2) ]

**VMUL      Multiply the components of two vectors**

VMUL ( V1, V2 ) = [ u1\*u2, v1\*v2 ]

**VQUO      Divide the components of two vectors**

VQUO ( V1, V2 ) = [ u1/u2, v1/v2 ]

**VSUB      Subtract the components of two vectors**

VSUB ( V1, V2 ) = [ u1-u2, v1-v2 ]

**VLT      Less than function**

VLT ( V, S ) = V IF |V| < S

**VLE      Less than or equal to function**

VLE ( V, S ) = V IF |V| <= S

**VGT      Greater than function**

VGT ( V, S ) = V IF |V| > S

**VGE      Greater than or equal to function**

VGE ( V, S ) = V IF |V| >= S

**VBTW      Between function**

VBTW ( V, S1, S2 ) = V IF S1 < |V| < S2

**VMSK      Masking function**

VMSK ( V, S ) = RMISSD IF S = RMISSD  
= V otherwise

## **GEMPAK Grid Diagnostic Functions**